noCollide

Nico Päller, Manuel Wilke

CONTENTS:

| 1 | NoCollide | 3 |
|-------|------------------------|----|
| 2 | Sensor | 5 |
| 3 | Driver | 9 |
| 4 | Data | 11 |
| 5 | Simulation Integration | 13 |
| 6 | Indices and tables | 15 |
| Index | | 17 |

The noCollide is a driver warning system to avoid collisions with objects. It can be implemented using LiDAR Sensors and a Raspberry Pi or the CARLA Simulator.

CONTENTS: 1

2 CONTENTS:

ONE

NOCOLLIDE

class lib.nocollide.TtcTimes(too_late: float, brake: float, warning: float)

A struct like class to enhance readability when storing Time-to-Collision values. too_late < brake < warning must be True

Parameters

- too_late (float) The time after which an accident is unavoidable
- brake (float) The time after which the driver must be braking to avoid an accident
- warning (float) The time after which the driver should be warned

Parameters

- driver (Driver) The configuration of the CAN-Bus to initialise
- sensors (SensorGroup) The sensor group, on which the calculation should be done
- ttc_times (Union[TtcTimes, None]) The times which define when to warn based on the TTC (Time-to-collision). If None, the default TTC-Times will be used: TtcTimes (too late=0.6, brake=1.6, warning=3.0)

calc()

The method that calculates the Time-to-Collision. Takes the Value of the sensor, that measures the closest object and calculates the relative velocity. The TTC results in dividing the distance by the relative velocity return:

```
run(block: bool = True)
```

The method to start the calculation. Can be run blocking (in an endless loop) or not (1 calulcation only)

Parameters block (bool) – wether the method should block or not

warn (ttc: float)

The method to warn the user based on the Time-to-Collision.

Parameters ttc(float) - the Time-to-Collision

TWO

SENSOR

```
class lib.sensor.SensorInterface
     An interface to implement a sensor with all the needed methods to function properly
     abstract change_addr (new_addr: int)
          A method to change the i2c address to be used with multiple devices on one bus
              Parameters new addr (int) – the new address that should be set
     abstract close()
          A method to close the sensor/bus
     abstract configure (mode: int)
          A method to apply any configuration to the sensor
              Parameters mode (int) – the mode that should be set
     abstract measure(rec_bias_corr: bool = True)
          Method to tell the sensor to measure a value
              Parameters rec_bias_corr (bool) – wether to measure with bias correction
     abstract read measurements() \rightarrow float
          Method to retrieve the measured data from the sensor
               Returns the measured data
              Return type float
class lib.sensor.Sensor (i2c bus: int = 1, max range: int = 50)
     The Class that handles a LiDAR Sensor
          Param i2c_bus: the bus number on which the sensor is running, defaults to Bus 1
     change_addr (new_addr: int)
          Method to change the I2C Address of the sensor
              Parameters new_addr (int) - the new address that should be set
     close()
          Method to close the bus
     configure (mode: int = 0)
          Method to initialize the sensor to different modi. Must be done before the sensor can be used
          configuration: Defaults to 0.
          0: Default mode, balanced performance
          1: Short range, high speed. Uses 0x1d maximum acquisition count
```

- 2: Default range, higher speed short range. Turns on quick termination detection for faster measurements at short range (with decreased accuracy)
- 3: Maximum range. Uses Oxff maximum acquisition count
- 4: High sensitivity detection. Overrides default valid measurement detection algorithm, and uses a threshold value for high sensitivity and noise
- **5**: Low sensitivity detection. Overrides default valid measurement detection algorithm, and uses a threshold value for low sensitivity and noise

Parameters mode (int) – the selected mode

```
measure (rec_bias_corr: bool = True)
```

Method to tell the sensor to take a measurement

Parameters rec_bias_corr (bool) – Wether the measurement should be taken with or without receiver bias correction; defaults to True

```
{\tt read\_measurements}\,(\,)\, 	o {\tt float}
```

Method to obtain the measured distance in cm

Returns the measured value in cm. Returns 0 if timeouted

Return type int

```
class lib.sensor.SensorGroup (i2c\_bus: int, sensors: Optional[lib.sensor.SensorInterface] = None, sensor\_names: Optional[List[str]] = None, init\_mode: int = 0) Class to connect to multiple sensors at once.
```

This class can be used in a context manager (with statement). It returns itself and then all Sensors which are being set (default: 3).

If not used in a with -Statement the bus must be closed manually using the close() method

```
with SensorGroup(i2c_bus=1) as (group, *sensors):
    ...
```

Parameters

- i2c_bus (int) the raspberry pi bus the sensors are running on
- sensor_names (Union[List[str], None]) a list of names, to identify the sensors. Defaults to ["left", "center", "right"] if None
- init_mode (int) the mode the sensors should be initialised with. Defaults to mode 0. See Sensor.configure() method

close()

Method do close and delete all sensors from the group. This method is also called when exiting the with-Statement

Parameters

- mode_num the mode number, referring to the mode if the <code>configure()</code> method of the <code>Sensor</code>
- **sensors** the sensornames of which the mode should be changed

Raises TypeError – TypeError when the is no such sensor in the group

6 Chapter 2. Sensor

start()

Method to start the measurements of the sensors. Launches a Thread for each sensor, where it measures continously in a loop

8 Chapter 2. Sensor

THREE

DRIVER

```
class lib.driver.Driver
     An interface to be used by the :py:class: noCollide <.nocollide.NoCollide> class get and set parameters regard-
     ing the vehicle
     \verb"abstract get_speed"() \to lib.data.Speed"
           A method to retrieve the current speed of the car
               Returns the current speed of the car
               Return type
                     py:class Speed <.data.Speed>
     abstract set_brake(val)
           A method to set the brake amount of the vehicle
               Parameters val (float) – the brake amound
     abstract set_throttle(val: float)
           A method to set the throttle of the vehicle
               Parameters val (float) – the throttle amound
     abstract warn()
          A method to warn the user for possible collisions
class lib.driver.CanConfig
     Class to better store config details of the can bus if necessary
class lib.driver.CanBus (conf: lib.driver.CanConfig, q_size: int = 1)
     \texttt{get\_speed}() \rightarrow lib.data.Speed
           Method to retrieve the speed from the queue
               Returns the latest speed sent via CAN
               Return type float
     run_forever()
          Method to keep in touch with the CAN-Bus. Runs in a thread, to avoid blocking
     set brake (val)
           A method to set the brake amount of the vehicle
               Parameters val (float) – the brake amound
     set_throttle(val: float)
           A method to set the throttle of the vehicle
```

Parameters val (float) – the throttle amound

warn()

A method to warn the user for possible collisions

10 Chapter 3. Driver

FOUR

DATA

class lib.data.Data(value: float, time: float)
class lib.data.Speed(value: float, time: float)
 A class to extend the :py:class: Data <.Data>. This class stores velocity values and the acceleration can be easily calculated
 acceleration(other: lib.data.Speed) → lib.data.Data
 A method to calculate the acceleration

Parameters other – the Speed before with which the Acceleration should be calculated

Returns the Acceleration

Return type

py:class Data <.Data>

class lib.data.Distance(value: float, time: float)

A class to extend the :py:class: *Data* <.*Data*>. This class stores distance values and the velocity can be easily calculated

velocity (*other*: lib.data.Distance) \rightarrow *lib.data.Speed*

A method to calculate the velocity. Returns Speed with value 1 if the times are the same

Parameters other – the Distance before with which the speed should be calculated

Returns the speed

Return type

py:class Speed <. Speed>

12 Chapter 4. Data

SIMULATION INTEGRATION

class lib.sim_interfaces.SimNoCollide(hud, *args, **kwargs)

A class to use the NoCollide in the Carla-Simulator. Simply integrates the HUD of the simulator to warn via the HUD rather than to warn via some kind of Bus

Parameters

- hud The HUD of the Simulation
- **args** Arguments to be passed to the parent class
- kwargs Keyword arguments to be passed to the parent class

warn (ttc: float)

Overwrites the parent warn Method to warn via the HUD rather than some kind of Bus :param ttc: the Time-to-Collision in seconds :type ttc: float

class lib.sim_interfaces.SimSensor(sensor, max_range=40)

A class to implement the Carla-Simulator object detection sensor. Due to the constant pushing nature of the Carla sensor, the last retrieved value and time must be saved to be ready when the NoCollide Algorithm requests the Value.

Parameters

- sensor the Carla sensor to use
- max_range the maximum range of the Carla Sensor

callback (data)

The callback method that is called, whenever the Carla sensor has measured new data. Simply stores the data, so taht i can be requested any time

Parameters data – the data measured by the carla sensor

change_addr (addr: int)

A method to change the i2c address to be used with multiple devices on one bus

Parameters new_addr (int) - the new address that should be set

close()

A method to close the sensor/bus

configure (mode: int)

A method to apply any configuration to the sensor

Parameters mode (int) – the mode that should be set

destroy()

Method to destroy the Sensor to free up memory when the simulation has ended

listen()

A Method to tell the Carla sensor to use the callback () method whenever a new value is measured

```
measure (rec_bias_corr: bool = True)
```

Method to tell the sensor to measure a value

Parameters rec_bias_corr (bool) – wether to measure with bias correction

```
read\_measurements() \rightarrow lib.data.Distance
```

The method of retrieve the newest Data of the Sensor. If the Carla Sensor hasn't measured anything yet, a <code>Distance</code> object will be returned with the maximum range. :return: the newest Distance measured by the Carla sensor :rtype: <code>Distance</code>

stop()

A method that is needed when stopping the simulation.

Class to overwrite the SensorGroup class to use the simulated sensor when retrieving the distance

```
\texttt{get\_closest}() \rightarrow lib.data.Distance
```

Class to overwrite the get_closest () method to use the simulated sensor when retrieving the distance :return:

SIX

INDICES AND TABLES

- genindex
- modindex
- search

INDEX

| acceleration() (lib.data.Speed method), 11 | measure() (lib.sim_interfaces.SimSensor method), 3 measure() (lib.sim_interfaces.SimSensor method), 14 | | |
|--|--|--|--|
| | N | | |
| C | | | |
| <pre>calc() (lib.nocollide.NoCollide method), 3</pre> | NoCollide, 1 | | |
| $\verb callback() (lib.sim_interfaces.SimSensor method), \\$ | NoCollide (class in lib.nocollide), 3 | | |
| 13 | R | | |
| CanBus (class in lib.driver), 9 | | | |
| CanConfig (class in lib.driver), 9 | read_measurements() (lib.sensor.Sensor method), | | |
| change_addr() (lib.sensor.Sensor method), 5 | 6 | | |
| change_addr() (lib.sensor.SensorInterface method), | read_measurements() (lib.sensor.SensorInterface | | |
| 5 | method), 5 | | |
| change_addr() (lib.sim_interfaces.SimSensor | read_measurements() (lib.sim_interfaces.SimSensor method), 14 | | |
| method), 13 close() (lib.sensor.Sensor method), 5 | run () (lib.nocollide.NoCollide method), 3 | | |
| close() (lib.sensor.Sensor method), 6 | run_forever() (lib.driver.CanBus method), 9 | | |
| close() (lib.sensor.SensorInterface method), 5 | Tan_rorever() (no.anver.eanbas memoa), | | |
| close() (lib.sim_interfaces.SimSensor method), 13 | S | | |
| configure () (lib.sensor.Sensor method), 5 | Sensor, 3 | | |
| configure () (lib.sensor.SensorInterface method), 5 | Sensor (class in lib.sensor), 5 | | |
| configure() (lib.sim_interfaces.SimSensor method), | SensorGroup (class in lib.sensor), 6 | | |
| 13 | SensorInterface (class in lib.sensor), 5 | | |
| П | <pre>set_brake() (lib.driver.CanBus method), 9</pre> | | |
| D | <pre>set_brake() (lib.driver.Driver method), 9</pre> | | |
| Data, 10 | <pre>set_mode() (lib.sensor.SensorGroup method), 6</pre> | | |
| Data (class in lib.data), 11 | set_throttle() (lib.driver.CanBus method), 9 | | |
| destroy() (lib.sim_interfaces.SimSensor method), 13 | set_throttle() (lib.driver.Driver method), 9 | | |
| Distance (class in lib.data), 11 | SimNoCollide (class in lib.sim_interfaces), 13 | | |
| Driver, 7 | SimSensor (class in lib.sim_interfaces), 13 | | |
| Driver (class in lib.driver), 9 | SimSensorGroup (class in lib.sim_interfaces), 14 | | |
| G | Simulation Integration, 11 Speed (class in lib.data), 11 | | |
| <pre>get_closest() (lib.sim_interfaces.SimSensorGroup</pre> | start() (lib.sensor.SensorGroup method), 6 | | |
| method), 14 | stop() (lib.sim_interfaces.SimSensor method), 14 | | |
| get_speed() (lib.driver.CanBus method), 9 | Scop (/ (no.sim_imerjaces.simsensor memou), 11 | | |
| get_speed() (lib.driver.Driver method), 9 | T | | |
| 1 | TtcTimes (class in lib.nocollide), 3 | | |
| L | | | |
| listen() (lib.sim_interfaces.SimSensor method), 13 | V | | |
| M | velocity() (lib.data.Distance method), 11 | | |
| measure() (lib.sensor.Sensor method), 6 | | | |

W

```
warn () (lib.driver.CanBus method), 10
warn () (lib.driver.Driver method), 9
warn () (lib.nocollide.NoCollide method), 3
warn () (lib.sim_interfaces.SimNoCollide method), 13
```

18 Index